

Lecture 5: Introduction to B-Spline Curves ¹

The control in shape change is better achieved with B -spline curves than the Bézier curves. The degree of the curve is not dependent on the total number of points. B -splines are made out several curve segments that are joined “smoothly”. Each such curve segment is controlled by a couple of consecutive control points. Thus, a change in the position of a control point only propagate upto a predictable range.

B -spline Polynomial

Let $\mathbf{p}_0, \dots, \mathbf{p}_n$ be the control points. The nonrational form of a B -spline is given by

$$\mathbf{p}(u) = \sum_{i=0}^n \mathbf{p}_i N_{i,D}(u)$$

For Bézier curves the number of control points determine the degree of the basis functions. For a B -spline curve a number D determines its degree which is $D - 1$.

The basis functions are defined recursively as follows:

$$\begin{aligned} N_{i,1}(u) &= 1 \text{ if } t_i \leq u < t_{i+1} \\ &= 0 \text{ otherwise} \end{aligned}$$

and

$$N_{i,d}(u) = \frac{(u - t_i)N_{i,d-1}(u)}{t_{i+d-1} - t_i} + \frac{(t_{i+d} - u)N_{i+1,d-1}(u)}{t_{i+d} - t_{i+1}}$$

The range of d is given by $d : d = 2, \dots, d = D$.

The t_j are called *knot* values, and a set of knots form a *knot* vector. If we have n control points and we want a B -spline curve of degree $D - 1$ we need $T = n + D + 1$ knots. If we impose the condition that the curve go through the end points of the control polygon, the knot values will be:

$$\begin{aligned} t_j &= 0 \text{ if } j < D \\ t_j &= j - D + 1 \text{ if } D \leq j \leq n \\ t_j &= n - D + 2 \text{ if } n < j \leq n + D \end{aligned}$$

The knots range from 0 to $n + D$, the index i of basis functions ranges from 1 to n . So, there are always $n + 1$ basis functions each of which depends on D knots. The knot vector takes the form

$$\mathbf{T} = \{\alpha, \dots, \alpha, t_D, \dots, t_n, \beta, \dots, \beta\}$$

where the end knots α and β are repeated with multiplicity D . We can parameterize the entire curve over $[0, 1]$. But, for simplicity we will use the interval $[\alpha = 0, \beta = n - D + 2]$. If we space the knots uniformly we get uniform B -splines. Otherwise, we get nonuniform B -splines as is done in the previous discussion.

¹Note by Tamal K. Dey

Basis functions

Let us assume that we have six control points ($n = 5$). Then, $N_{i,1}$ will require $5 + 1 + 1 = 7$ knots $\{0, 1, 2, 3, 4, 5, 6\}$. We obtain:

$$\begin{aligned}
 N_{0,1}(u) &= 1 \text{ if } 0 \leq u < 1 \\
 &= 0 \text{ otherwise} \\
 N_{1,1}(u) &= 1 \text{ if } 1 \leq u < 2 \\
 &= 0 \text{ otherwise} \\
 &\vdots \\
 &\vdots \\
 N_{5,1}(u) &= 1 \text{ if } 5 \leq u \leq 6 \\
 &= 0 \text{ otherwise}
 \end{aligned}$$

These are box functions and the corresponding B -spline is $\mathbf{p}(u) = \mathbf{p}_i$ for $i \leq u < i + 1$, i.e., the control points itself.

Now lets consider the basis functions $N_{i,2}(u)$. This will need $N_{i,1}$'s.

$$\begin{aligned}
 N_{0,2}(u) &= 1 \text{ if } u = 0 \\
 &= 0 \text{ otherwise} \\
 N_{1,2}(u) &= 1 \text{ if } 0 \leq u < 1 \\
 &= 0 \text{ otherwise} \\
 &\vdots \\
 &\vdots \\
 N_{5,2}(u) &= 1 \text{ if } 4 \leq u < 5 \\
 &= 0 \text{ otherwise}
 \end{aligned}$$

This gives:

$$\begin{aligned}
 N_{0,2}(u) &= (1 - u)N_{1,1}(u) \\
 N_{1,2}(u) &= uN_{1,1}(u) + (2 - u)N_{2,1}(u) \\
 N_{2,2}(u) &= (u - 1)N_{2,1}(u) + (3 - u)N_{3,1}(u) \\
 N_{3,2}(u) &= (u - 2)N_{3,1}(u) + (4 - u)N_{4,1}(u) \\
 N_{4,2}(u) &= (u - 3)N_{4,1}(u) + (5 - u)N_{5,1}(u) \\
 N_{5,2}(u) &= (u - 4)N_{5,1}(u)
 \end{aligned}$$

We have the curve:

$$\begin{aligned}
 \mathbf{p}(u) &= (1 - u)\mathbf{p}_0 + u\mathbf{p}_1 \quad 0 \leq u < 1 \\
 &= (2 - u)\mathbf{p}_1 + (u - 1)\mathbf{p}_2 \quad 1 \leq u < 2 \\
 &= (3 - u)\mathbf{p}_2 + (u - 2)\mathbf{p}_3 \quad 2 \leq u < 3 \\
 &= (4 - u)\mathbf{p}_3 + (u - 3)\mathbf{p}_4 \quad 3 \leq u < 4 \\
 &= (5 - u)\mathbf{p}_4 + (u - 4)\mathbf{p}_5 \quad 4 \leq u < 5
 \end{aligned}$$

These are the line segments joining the control points.